

## SHT7x PSoC Component

Generated by Doxygen 1.8.14



# Contents

<b>1</b>	<b>File Index</b>	<b>1</b>
1.1	File List	1
<b>2</b>	<b>File Documentation</b>	<b>3</b>
2.1	SHT7x.h File Reference	3
2.1.1	Detailed Description	4
2.1.2	Macro Definition Documentation	5
2.1.2.1	SHT7x_BATTERY_LOW	5
2.1.2.2	SHT7x_BATTERY_OK	5
2.1.2.3	SHT7x_BLOCK	5
2.1.2.4	SHT7x_ERR_CRC	5
2.1.2.5	SHT7x_ERR_NO_ACK	5
2.1.2.6	SHT7x_ERR_TO	5
2.1.2.7	SHT7x_MEAS_READY	5
2.1.2.8	SHT7x_NON_BLOCK	6
2.1.2.9	SHT7x_READ_HUMI	6
2.1.2.10	SHT7x_READ_TEMP	6
2.1.3	Function Documentation	6
2.1.3.1	SHT7x_ActivateHeater()	6
2.1.3.2	SHT7x_ActivateOTPREload()	6
2.1.3.3	SHT7x_CalcDewpoint()	6
2.1.3.4	SHT7x_CalcHum()	7
2.1.3.5	SHT7x_CalcTemp()	7
2.1.3.6	SHT7x_DeactivateOTPREload()	8

2.1.3.7	SHT7x_GetByte()	8
2.1.3.8	SHT7x_GetResult()	8
2.1.3.9	SHT7x_Meas()	9
2.1.3.10	SHT7x_MeasReady()	9
2.1.3.11	SHT7x_Measure()	9
2.1.3.12	SHT7x_MeasureHumi()	10
2.1.3.13	SHT7x_MeasureTemp()	10
2.1.3.14	SHT7x_PutByte()	11
2.1.3.15	SHT7x_ReadSR()	11
2.1.3.16	SHT7x_Reset()	12
2.1.3.17	SHT7x_ResetConnection()	12
2.1.3.18	SHT7x_SetHighResolution()	12
2.1.3.19	SHT7x_SetLowResolution()	12
2.1.3.20	SHT7x_Start()	12
2.1.3.21	SHT7x_StartMeasure()	13
2.1.3.22	SHT7x_StartMeasureHumi()	13
2.1.3.23	SHT7x_StartMeasureTemp()	13
2.1.3.24	SHT7x_StartTransmission()	14
2.1.3.25	SHT7x_WriteSR()	14

# Chapter 1

## File Index

### 1.1 File List

Here is a list of all documented files with brief descriptions:

<a href="#">SHT7x.h</a>	Header file for interfacing with a SHT7x sensor . . . . .	<a href="#">3</a>
-------------------------	---	-------------------



## Chapter 2

# File Documentation

### 2.1 SHT7x.h File Reference

Header file for interfacing with a SHT7x sensor.

```
#include "cytypes.h"
#include "CyLib.h"
```

#### Macros

- `#define SHT7x_ERR_NO_ACK 1`
- `#define SHT7x_ERR_CRC 2`
- `#define SHT7x_ERR_TO 3`
- `#define SHT7x_MEAS_READY 4`
- `#define SHT7x_READ_TEMP 0`
- `#define SHT7x_READ_HUMI 1`
- `#define SHT7x_BLOCK 1`
- `#define SHT7x_NON_BLOCK 0`
- `#define SHT7x_BATTERY_LOW 1`
- `#define SHT7x_BATTERY_OK 0`

#### Functions

- `uint8_t SHT7x_Start (void)`  
*Start the component.*
- `uint8_t SHT7x_Measure (float *temp, float *humi, float *dew)`  
*Complete blocking measurement.*
- `uint8_t SHT7x_MeasureTemp (float *temp)`  
*Temperature blocking measurement.*
- `uint8_t SHT7x_MeasureHumi (float *humi, float temp)`  
*Humidity blocking measurement.*
- `uint8_t SHT7x_StartMeasure (uint8_t cmd)`  
*Initiate measurement.*
- `uint8_t SHT7x_StartMeasureTemp ()`

- Initiate non blocking temperature measurement.*
- uint8\_t [SHT7x\\_StartMeasureHumi](#) ()
- Initiate non blocking humidity measurement.*
- uint8\_t [SHT7x\\_Meas](#) (uint8\_t cmd, uint16\_t \*result, int block)
- Initiate measurement.*
- uint8\_t [SHT7x\\_MeasReady](#) (void)
- Check if non-blocking measurement has completed.*
- uint8\_t [SHT7x\\_PutByte](#) (char command)
- Write a byte to the sensor and check acknowledgement.*
- uint8\_t [SHT7x\\_GetByte](#) (int ack)
- Get a byte from the sensor.*
- void [SHT7x\\_StartTransmission](#) (void)
- Generate Sensirion-specific transmission start sequence.*
- void [SHT7x\\_ResetConnection](#) (void)
- Reset connection with sensor.*
- uint8\_t [SHT7x\\_Reset](#) (void)
- Public reset function.*
- uint8\_t [SHT7x\\_GetResult](#) (uint16\_t \*result)
- Get measurement result from sensor (plus CRC, if enabled)*
- uint8\_t [SHT7x\\_ReadSR](#) (uint8\_t \*result)
- Read to status register.*
- uint8\_t [SHT7x\\_WriteSR](#) (uint8\_t value)
- Write to status register.*
- uint8\_t [SHT7x\\_SetHighResolution](#) (void)
- Set resolution to high.*
- uint8\_t [SHT7x\\_SetLowResolution](#) (void)
- Set resolution to low.*
- uint8\_t [SHT7x\\_ActivateOTPREload](#) (void)
- Activate OTP Reload.*
- uint8\_t [SHT7x\\_DeactivateOTPREload](#) (void)
- Deactivate OTP Reload.*
- uint8\_t [SHT7x\\_ActivateHeater](#) (void)
- Activate on chip heater.*
- uint8\_t [SHT7x\\_DeactivateHeater](#) (void)
- Deactivate on chip heater.*
- uint8\_t [SHT7x\\_CheckEndOfBattery](#) (void)
- Check if vdd value is below 2.47 V.*
- float [SHT7x\\_CalcTemp](#) (uint16\_t rawData)
- Calculate temperature in degrees C.*
- float [SHT7x\\_CalcHum](#) (uint16\_t rawData, float temp)
- Calculate relative humidity with temperature compensation.*
- float [SHT7x\\_CalcDewpoint](#) (float humi, float temp)
- Calculate dewpoint.*

### 2.1.1 Detailed Description

Header file for interfacing with a SHT7x sensor.

This header contains macros and function prototypes to interface the PSoC with a Sensirion SHT7x temperature and humidity sensor. This work is based on the Sensirion SHT7x Arduino library written by Carl Jackson: <https://github.com/spease/Sensirion>

#### Author

Davide Marzorati



## 2.1.2 Macro Definition Documentation

### 2.1.2.1 SHT7x\_BATTERY\_LOW

```
#define SHT7x_BATTERY_LOW 1
```

Value returned when battery is low

### 2.1.2.2 SHT7x\_BATTERY\_OK

```
#define SHT7x_BATTERY_OK 0
```

Value returned when battery is ok

### 2.1.2.3 SHT7x\_BLOCK

```
#define SHT7x_BLOCK 1
```

Value to pass to functions to start blocking measurements

### 2.1.2.4 SHT7x\_ERR\_CRC

```
#define SHT7x_ERR_CRC 2
```

Error code for CRC failure.

### 2.1.2.5 SHT7x\_ERR\_NO\_ACK

```
#define SHT7x_ERR_NO_ACK 1
```

Error code for acknowledgment not received.

### 2.1.2.6 SHT7x\_ERR\_TO

```
#define SHT7x_ERR_TO 3
```

Error code for measurement timeout.

### 2.1.2.7 SHT7x\_MEAS\_READY

```
#define SHT7x_MEAS_READY 4
```

Value returned when measurement is ready

### 2.1.2.8 SHT7x\_NON\_BLOCK

```
#define SHT7x_NON_BLOCK 0
```

Value to pass to functions to start non-blocking measurements

### 2.1.2.9 SHT7x\_READ\_HUMI

```
#define SHT7x_READ_HUMI 1
```

Value to pass to read humidity.

### 2.1.2.10 SHT7x\_READ\_TEMP

```
#define SHT7x_READ_TEMP 0
```

Helper value to use as a parameter to read temperature.

## 2.1.3 Function Documentation

### 2.1.3.1 SHT7x\_ActivateHeater()

```
uint8_t SHT7x_ActivateHeater (
    void )
```

Activate on chip heater.

Calling this function activates the on chip heater. The heater may increase the temperature of the sensor by 5-10°C (9-18°F) beyond ambient temperature. The heater draw 8ma @ 5 V supply voltage. The heater can be helpful for functionality analysis. Humidity and temperature readings before and after applying the heater are compared. Temperature shall increase while relative humidity decreases at the same time. Dew point shall remain the same.

Note: the temperature reading will display the temperature of the heated sensor element and not the ambient temperature. Furthermore, the sensor is not qualified for continuous application of the heater.

### 2.1.3.2 SHT7x\_ActivateOTPREload()

```
uint8_t SHT7x_ActivateOTPREload (
    void )
```

Activate OTP Reload.

If this is called, the calibration data are uploaded to the register before each measurement. This increases measurement time by about 10 ms.

### 2.1.3.3 SHT7x\_CalcDewpoint()

```
float SHT7x_CalcDewpoint (
    float humi,
    float temp )
```

Calculate dewpoint.

Starting from the value of humidity and temperature, it computes the dewpoint value

**Parameters**

<i>humi</i>	humidity
<i>temp</i>	temperature

**Returns**

dewpoint value

**2.1.3.4 SHT7x\_CalcHum()**

```
float SHT7x_CalcHum (
    uint16_t rawData,
    float temp )
```

Calculate relative humidity with temperature compensation.

Starting from the raw sensor data, returns the value of relative humidity with temperature compensation.

**Parameters**

<i>rawData</i>	raw sensor data
<i>temp</i>	value of temperature

**Returns**

relative humidity (%)

**2.1.3.5 SHT7x\_CalcTemp()**

```
float SHT7x_CalcTemp (
    uint16_t rawData )
```

Calculate temperature in degrees C.

Starting from the raw sensor data, returns the temperature in degrees (C).

**Parameters**

<i>rawData</i>	raw sensor data
----------------	-----------------

**Returns**

temperature in degrees C

### 2.1.3.6 SHT7x\_DeactivateOTPREload()

```
uint8_t SHT7x_DeactivateOTPREload (
    void )
```

Deactivate OTP Reload.

If this is called, the calibration data are not uploaded to the register before each measurement. This reduces measurement time by about 10 ms.

### 2.1.3.7 SHT7x\_GetByte()

```
uint8_t SHT7x_GetByte (
    int ack )
```

Get a byte from the sensor.

This function gets a byte from the sensor and allows to choose if doing or skipping the acknowledgement.

#### Parameters

<i>ack</i>	0 if no ack, 1 if ack
------------	-----------------------

#### Returns

the byte read

### 2.1.3.8 SHT7x\_GetResult()

```
uint8_t SHT7x_GetResult (
    uint16_t * result )
```

Get measurement result from sensor (plus CRC, if enabled)

#### Parameters

<i>result</i>	Variable where the result will be stored
---------------	--

#### Return values

<i>S_Err_CRC</i>	if CRC check failed
0	if everything ok

### 2.1.3.9 SHT7x\_Meas()

```
uint8_t SHT7x_Meas (
    uint8_t cmd,
    uint16_t * result,
    int block )
```

Initiate measurement.

This functions starts a measurement, and if this is blocking it waits until the measurement is complete before returning.

#### Parameters

<i>cmd</i>	SHT7x_TEMP for temperature, SHT7x_HUMI for humidity
<i>result</i>	Variable where to store the result
<i>block</i>	True if blocking

#### Return values

<i>SHT7x_ERR_NO_ACK</i>	If the sensor did not acknowledge
<i>SHT7x_ERR_CRC</i>	If CRC check failed
<i>SHT7x_ERR_TO</i>	If there was a timeout in the measurement

### 2.1.3.10 SHT7x\_MeasReady()

```
uint8_t SHT7x_MeasReady (
    void )
```

Check if non-blocking measurement has completed.

Non-zero return indicates complete.

#### Returns

SHT7x\_MEAS\_READY 0 if measurement is complete

### 2.1.3.11 SHT7x\_Measure()

```
uint8_t SHT7x_Measure (
    float * temp,
    float * humi,
    float * dew )
```

Complete blocking measurement.

This functions performs a blocking measurement for both temperature and humidity values.

**Parameters**

<i>temp</i>	Variable where the temperature value will be stored
<i>humi</i>	Variable where the humidity value will be stored
<i>dew</i>	Variable where the dewpoint value will be stored

**Return values**

<i>SHT7x_ERR_NO_ACK</i>	If the sensor did not acknowledge
<i>SHT7x_ERR_CRC</i>	If CRC check failed
<i>SHT7x_ERR_TO</i>	If there was a timeout in the measurement
<i>0</i>	If everything ok

**2.1.3.12 SHT7x\_MeasureHumi()**

```
uint8_t SHT7x_MeasureHumi (
    float * humi,
    float temp )
```

Humidity blocking measurement.

This functions performs a blocking measurement for humidity.

**Parameters**

<i>humi</i>	Variable where the humidity value will be stored
<i>temp</i>	Value of temperature

**Return values**

<i>SHT7x_ERR_NO_ACK</i>	If the sensor did not acknowledge
<i>SHT7x_ERR_CRC</i>	If CRC check failed
<i>SHT7x_ERR_TO</i>	If there was a timeout in the measurement
<i>0</i>	If everything ok

**2.1.3.13 SHT7x\_MeasureTemp()**

```
uint8_t SHT7x_MeasureTemp (
    float * temp )
```

Temperature blocking measurement.

This functions performs a blocking measurement for temperature.

## Parameters

<i>temp</i>	Variable where the temperature value will be stored
-------------	---

## Return values

<i>SHT7x_ERR_NO_ACK</i>	If the sensor did not acknowledge
<i>SHT7x_ERR_CRC</i>	If CRC check failed
<i>SHT7x_ERR_TO</i>	If there was a timeout in the measurement
<i>0</i>	If everything ok

## 2.1.3.14 SHT7x\_PutByte()

```
uint8_t SHT7x_PutByte (  
    char d )
```

Write a byte to the sensor and check acknowledgement.

This function sends a byte to the sensor and check if the sensor acknowledged it. The sensor returns a value greater than 0 if no acknowledgement was received.

## Parameters

<i>d</i>	the byte to write
----------	-------------------

## Return values

<i>S_Err_NoAck</i>	if no ack
<i>0</i>	if everything ok

## 2.1.3.15 SHT7x\_ReadSR()

```
uint8_t SHT7x_ReadSR (  
    uint8_t * result )
```

Read to status register.

## Parameters

<i>result</i>	Variable where the SR byte will be stored
---------------	---

## Return values

<i>S_Err_NoAck</i>	if no acknowledgement was received
--------------------	------------------------------------

**Return values**

0	otherwise
---	-----------

**2.1.3.16 SHT7x\_Reset()**

```
uint8_t SHT7x_Reset (
    void )
```

Public reset function.

Reset communication and reset status register to default

**2.1.3.17 SHT7x\_ResetConnection()**

```
void SHT7x_ResetConnection (
    void )
```

Reset connection with sensor.

Set up a predefined sequence of signals on clock and data line to restore a connection with the sensor.

**2.1.3.18 SHT7x\_SetHighResolution()**

```
uint8_t SHT7x_SetHighResolution (
    void )
```

Set resolution to high.

Resolution is set to 12 bits for humidity, and to 14 bits for temperature

**2.1.3.19 SHT7x\_SetLowResolution()**

```
uint8_t SHT7x_SetLowResolution (
    void )
```

Set resolution to low.

Resolution is set to 8 bits for humidity, and to 12 bits for temperature

**2.1.3.20 SHT7x\_Start()**

```
uint8_t SHT7x_Start (
    void )
```

Start the component.

This function should always be called before starting any measurements, since it sets up the sensor based on the parameters specified in the top design.



## Return values

<i>SHT7x_ERR_NO_ACK</i>	if no acknowledgment was received
<i>0</i>	if everything ok

## 2.1.3.21 SHT7x\_StartMeasure()

```
uint8_t SHT7x_StartMeasure (
    uint8_t cmd )
```

Initiate measurement.

This functions starts a measurement for temperature or humidity based on the passed parameter.

## Parameters

<i>cmd</i>	SHT7x_TEMP for temperature, SHT7x_HUMI for humidity
------------	---

## Return values

<i>SHT7x_ERR_NO_ACK</i>	If the sensor did not acknowledge
<i>0</i>	If everything ok

## 2.1.3.22 SHT7x\_StartMeasureHumi()

```
uint8_t SHT7x_StartMeasureHumi ( )
```

Initiate non blocking humidity measurement.

This functions starts a non blocking measurement for humidity.

## Return values

<i>SHT7x_ERR_NO_ACK</i>	If the sensor did not acknowledge
<i>0</i>	If everything ok

## 2.1.3.23 SHT7x\_StartMeasureTemp()

```
uint8_t SHT7x_StartMeasureTemp ( )
```

Initiate non blocking temperature measurement.

This functions starts a non blocking measurement for temperature.

## Return values

<i>SHT7x_ERR_NO_ACK</i>	If the sensor did not acknowledge
<i>0</i>	If everything ok

**2.1.3.24 SHT7x\_StartTransmission()**

```
void SHT7x_StartTransmission (
    void )
```

Generate Sensirion-specific transmission start sequence.

This is where Sensirion does not conform to the I2C standard.

**2.1.3.25 SHT7x\_WriteSR()**

```
uint8_t SHT7x_WriteSR (
    uint8_t value )
```

Write to status register.

## Parameters

<i>value</i>	the byte to write to status register
--------------	--------------------------------------

## Return values

<i>S_Err_NoAck</i>	if no acknowledgement was received
<i>0</i>	otherwise